

## Camera Viewer Program Information

### Quick Start:

Make *any number* of JPG images 400w by 300h in size.

Name them sequentially (ex. 1.jpg, 2.jpg, 3.jpg .....110.jpg)

Put them in the 'FILMCAN' folder

Rename the web page file to reflect the number of images in the FILMCAN folder, the name portion can be renamed to *anything* you like. (ex. If you have 12 JPG images in the FILMCAN folder, the name of the file can be MyVacation-12.html, or lookATthis-12.htm or skydiving-12.html, etc.)

Open the web page in any browser to view your images

---

### Full Viewer Information:

The downloaded zip file contains the following:

- A folder named 'FILMCAN', which is where you would put all of your images. This folder must not be renamed. The folder contains 3 of our images as examples. You would replace them with your own images .

The 'FILMCAN' folder can contain as many jpg images as you want to view.

The images must be 400 pixels wide by 300 pixels tall.

This viewer is for horizontal images only. There is a vertical image player also available for download on our site.

Name the images sequentially (ex. 1.jpg, 2.jpg, 3.jpg .....110.jpg)

- The Flash viewer program named 'PPCAMERA.SWF'. This file must not be renamed.
- A web page that shows the viewer program. It can be played from your computer's hard drive or be put online and linked to. Just remember to keep the web page, FILMCAN folder and PPCAMERA.SWF in the same directory or folder, in order to operate properly.

You can rename this web page file to anything you would like as long as the extension is a standard web page extension (ex .htm, .html, .shtml ). The file name also reflects the number of images that you've put in the 'FILMCAN' folder.

For example, if you wanted to call the page MyDogAndCat and you had 14 images in the folder. You would name the file *MyDogAndCat-14.html*.

Note: Between the name and the number is a standard hyphen -

- This PDF document
-

## Viewer controls:

The viewer can display your images automatically by clicking the 'AutoRun ' On button. You can vary the speed in which the images cycle by selecting any of the speed buttons. They range from slow to fast. You go back to manual advance by clicking the 'AutoRun ' Off button.

The number of the image that you are viewing and the total number of images in the 'FILMCAN' folder is displayed on the control panel.

The "camera's dial" will navigate the images by going to the first image, going backward, going forward and going to the last image.

There are three transitions between images that you can select. No transition, Fade transition and Sliding transition.

